

## Setting up POP3 and IMAP4 email, and MSN on Windows Mobile devices

To configure POP3, IMAP4, and SMTP on a Pocket PC Phone, perform the following steps:

1. On the Today screen, tap **Start**, and then tap **Messaging**.
2. To create a new account, on the Text Messages screen, tap **Menu**, tap **Tools**, and then tap **New Account**.
3. To retrieve your e-mail settings, on the **E-mail Setup (1/5)** page, in the **Enter e-mail address** box, type your e-mail address.
4. On the **E-mail Setup (2/5)** page, tap **Next**.

**Note:** Auto configuration attempts to download the necessary e-mail server settings so that you do not need to enter them manually.

5. On the **E-mail Setup (3/5)** page, in the **Your name** box, type your name. In the **Password** box, type your password, and then tap **Next**. If the auto configuration was successful, your user name is already entered.
6. On the **E-mail Setup (4/5)** page, in the **Account type** list, select either POP3 or IMAP4. In the **Name** box, type an account name, and then tap **Next**.
7. On the **E-mail Setup (5/5)** page, tap **Finish**. In the **Messaging** message box, tap **Yes**.

To configure POP3, IMAP4, and SMTP on a Smartphone, perform the following steps:

1. On the Home screen, click **Start**.
2. On the Start screen, click **Messaging**. On the Messaging screen, click **New Account**.
3. Select your email provider and click **Next**.
4. To retrieve your e-mail settings from the Internet, on the Email Setup screen, in the **Your name** box, type your account name. In the **Email address** box, type your email address. Ensure that the **Attempt to obtain email settings from the Internet** check box is selected, and then click **Next**. Auto configuration will attempt to download settings automatically.

**Note:** It is not always possible for a device to collect your email settings automatically, especially in the case of a personalized domain. In these instances you will see the message “**could not obtain email settings**” and you must enter this information manually, shown below from Step 5.

5. Click **Next**.
6. Enter your **User Name**, **Domain** (if required) and **Password** and then click **Next**.
7. Enter the **Server Type** and **Account Name** (the name by which your account will be listed on your Windows Mobile device). Click **Next**.
8. Enter your **Incoming Server** (specified by your email host/ISP) and an **Outgoing Server\***. Click **Next**

\*The Outgoing Server should be set to one of the following:

O2 network devices: **smtp.o2.co.uk**  
Vodafone: **send.vodafone.net**

9. You next have the choice of selecting to download past emails to the device, and also a size limitation for each message to prevent heavy data use. Click **Next**.
10. Finally you can select how often the device will connect to your mailbox to collect email messages. The minimum is every fifteen minutes. Click **Next**.
11. Click **Finish**.

You will now be given the option to check for email messages.

To configure Hotmail and MSN Messenger:

1. On the Today screen, tap **Start**, and then tap **Pocket MSN**.
2. To access your Hotmail account, on the Pocket MSN screen, tap **MSN Hotmail**.
3. To sign in, in the **E-mail address** box, type your e-mail address, and in the **Password** box, type your password, and then tap **Sign In**.
4. To access MSN Messenger, on the Pocket MSN screen, tap **MSN Messenger**.
5. On the MSN Messenger screen, tap **Sign In**.
6. To sign in, in the **E-mail address** box, type your e-mail address, and in the **Password** box, type your password, and then tap **Sign In**.